

Architecture · Rbac

Generated Tue, Sep 22, 2026 12:14 PM · Single page

RBAC (roles & permissions)

Custom role-based access control. Permissions are defined in config and synced to the database — **Spatie Permission is not used.**

Model

[Diagram omitted in PDF — open this page in the online docs to view it.]

- Permission slug format: {action}.{module}
Examples: view.leads, manage.channels, reply.inbox
- Roles are **per company** (after migrations that added roles.company_id).
- System role admin receives all permissions (*).
- Default role sales receives an explicit allow-list.

Modules & actions

Source: config/permissions.php.

Module	Actions
customers	view, create, import, update, delete
leads	view (own), view_all, create, import, update, delete, assign, convert, log
tasks	view (own), view_all, create, change_status, update, delete, assign
users	view, create, import, update, delete
roles	view, create, update, delete
activity_logs	view, view_own
notifications	view
company_settings	update
reports	view, export
demo	website_lead
channels	view, manage
inbox	view, reply, assign

Default sales grants

Exact list from database/seeder/RbacSeeder.php:

- view/create/import/update/delete.customers

- `view/create/import/update/delete/convert/log.leads` (no `view_all.leads`, no `assign.leads`)
- `view/change_status/update/delete.tasks` (no `create.tasks`, `view_all.tasks`, `assign.tasks`)
- `view_own.activity_logs`, `view.notifications`
- `view/export.reports`
- `view.channels` (no `manage.channels`)
- `view.inbox`, `reply.inbox` (no `assign.inbox`)

Admin (*) receives every synced permission. After custom Role UI edits, the database is source of truth.

Syncing permissions

Whenever you change `config/permissions.php`:

```
php artisan permissions:sync
```

This will:

1. Upsert permission rows for every `{action}.{module}`.
2. Delete stale permissions (and detach them from roles).
3. Sync default roles via `RbacRoleSynchronizer`.
4. Refresh gates.

Authorization in code

Mechanism	Usage
<code>\$user->hasPermission('view.inbox')</code>	Direct check
<code>\$this->authorize('view', \$model)</code>	Policy
<code>@can('manage', \$channel)</code>	Blade
<code>middleware('permission:view.notifications')</code>	Route

Gates are registered from DB permissions by `PermissionRegistrar`.

AdminLTE menu

Sidebar entries use `'can' => 'view.channels'`-style gate abilities (`config/adminlte.php`). Missing menu after deploy usually means permissions were not synced.

Adding a permission

1. Add module/action in `config/permissions.php`.
2. Run `php artisan permissions:sync`.
3. Grant on roles (UI or update `RbacSeeder` defaults).
4. Enforce via policy / middleware / `@can`.
5. Add Feature tests for allow/deny.

Related

- [Multi-tenancy](#)
- [Modules overview](#)
- [Contributing](#)